



An Elevator Mechanic's Guide to Using Alpha+ (the Lykos App)

PART II: DOWNLOAD PARAMETERS

(This guide assumes the user has the latest version of Alpha+ on their phone)

1. CLICK ON THE ALPHA PLUS ICON!




Figure 1.

2. CONNECT TO YOUR LYKOS CONTROLLER! *(Follow the ordered steps below)*


Note: For phones with Android Version 11 or lower, please go into your settings and turn ON Location and Bluetooth. Location Permission for the Alpha+ app will also need to be enabled if not already.

#1




Note: The name of your Lykos controller's Bluetooth will be the job name.

#2



#3

Note: After clicking on your controller, you will arrive at this screen. Continue to the next step.



3. PUT YOUR LYKOS CONTROLLER INTO PROGRAM MODE!

- a. Turn on INSPECT (MR) and hold down CAPTURE CAR for 5 seconds.

#1.



#2.



b. You will see PROGRAM MODE and get fault F126: PROGRAM MODE

#1.




#2.




4. CLICK ON “PARAMETERS”

10:26 5G 100%





Note: If the Lykos Controller is not on “Program Mode”, clicking on “Parameters” will open a warning advising to put the car on “Program Mode”.


10:05 5G 92%



5. CLICK ON “DOWNLOAD TO PHONE”, THEN CLICK “CONFIRM”



6. DOWNLOADING PARAMETERS PROCESS



7. DOWNLOAD COMPLETE



8. THAT CONCLUDES THE “PART 11: DOWNLOAD PARAMETERS” GUIDE.

Thank you for using the Alpha+ app. We hope you have a great day.

If you have any questions, please feel free to contact our technical support team at:
support@alphaelevatorcontrol.com or (916) 957-5900.